



ChatSimTM

Authorized Distributor

設定説明書

2016/03/04 版

～ 目次 ～

はじめて Chat Sim をご購入されたお客様むけ

◆開通までの流れ（アクティベート方法）

．．．．． 3ページ

既に Chat Sim ご利用のお客様むけ

◆マルチメディアクレジット設定の仕方

．．．．． 9ページ

◆Android端末設定の仕方 ．． 11ページ

開通までの流れ (アクティベート方法)

ご利用の流れ (SIM 開通まで)

SIM 購入

アクティベート
英語サイト



Chat SIM
開通

SIM購入後、
アクティベート（利用開始の申請）が必要となります。

アクティベートは、インターネット上で行うことが可能です。英語サイトでのアクティベートとなるため、本資料では入力内容や手順をご案内いたします。

SIM購入がお済みでないお客様は、
公式ストア（ <http://chatsimjp.com/store/> ）より、
ご購入ください。

開通までの流れ（アクティベート方法）

まずは、Chat Simのアクティベートページ(英語)にアクセスします。

Chat Sim アクティベートページ


<https://www.chatsim.com/en/activate>

アクティベートページでは、以下の手順で各項目を入力していきます。

- 1) Simカードに記載されている番号の入力
- 2) 新規アカウント作成
- 3) パーソナルデータの入力
- 4) アクティベート完了

開通までの流れ (アクティベート方法)

1) Simカードに記載されている番号の入力




The screenshot shows the ChatSim activation interface. At the top, there is a navigation bar with the ChatSim logo and links for Overview, Plan, Blog, Support, and Login. On the right, there are buttons for Activate, Recharge, and Buy now, along with a language dropdown set to EN. The main heading is "Activate your ChatSim". Below this, there is a progress bar with three steps: a SIM card icon (active), a person icon, and a checkmark icon. A text instruction reads: "To register your ChatSim, enter the ID code of the SIM Card (19 or 20-digit number), the ChatSim mobile number and press 'Next'". Below this, there is a green link: "If you have a coupon code, use it to receive a bonus recharge". A "Coupon Code" input field is provided. The "ChatSim Data" section is highlighted with a red dashed border and contains two input fields: "Sim Card identifier (19 or 20 digits number) *" and "ChatSim Number *". Below these fields is a "Next" button. An inset image of a SIM card is shown below the input fields. A purple arrow points from the "Sim Card identifier" field to the SIM card's orange label, which contains the number "+441234567890". A red arrow points from the "ChatSim Number" field to the SIM card's white label, which contains the number "8912345678901234567".

Sim Card identifierとChatsim Numberを入れ、Nextをクリックします

開通までの流れ（アクティベート方法）

2) 新規アカウント作成



The screenshot shows the ChatSim activation page. At the top, there is a navigation bar with the ChatSim logo, links for Overview, Plan, Blog, Support, and Login, and buttons for Activate, Recharge, Buy now, and EN. The main heading is "Activate your ChatSim". Below this, there is a progress bar with three steps: a server icon, a person icon, and a checkmark icon. The first step is active. The second step is a registration form with two options: "Are you already registered?" and "Haven't you registered yet?". The "Are you already registered?" form has fields for Username and Password, a checkbox for terms and conditions, a "Next" button, and a "Forgot Password" link. The "Haven't you registered yet?" form has a "Next" button. A red dashed box highlights the "Next" button in the "Haven't you registered yet?" form, with the text "こちらをクリック" (Click here) written in red above it. A "Go back" button is located at the bottom center.

右の「Haven't you registered yet?」のNextをクリックします

開通までの流れ (アクティベート方法)

3) パーソナルデータの入力



The screenshot shows the 'Activate your ChatSim' web form. At the top, there is a navigation bar with 'Overview', 'Plan', 'Blog', 'Support', and 'Login' links, along with 'Activate', 'Recharge', and 'Buy now' buttons. The main heading is 'Activate your ChatSim'. Below this is a progress bar with three steps: a SIM card icon, a person icon, and a checkmark icon. The 'Personal Data' section contains the following fields:

- Name: Mr. (dropdown), Taro (input)
- Last Name: Yamada (input)
- Address: 201 9-9 Rokuban-cho (input)
- ZIP CODE: 1020085 (input)
- City: Chiyoda-ku (input)
- State/Province: Tokyo (input)
- Country: Japan (dropdown)
- E-mail: XXX@XXX.XXX (input)
- Confirm E-mail: XXX@XXX.XXX (input)
- Mobile: +81 [頭の0を外した番号] (input)
- Identity Document: 免許証 / パスポート / 健康保険証 / 学生証 など (input) with a 'Browse ...' button

At the bottom, there are two mandatory fields with checkboxes:


- I have read the information on the processing of personal data and I consent to the use of my data to receive technical and promotional communications from Chatsim about its products or services, as specified in section 3 of the Information Sheet available at www.chatsim.com.
- I ask Chatsim S.r.l. proceeding with the activation. I agree to the General Terms and Conditions and rates available on the website www.chatsim.com by sending or receiving the first message.

At the bottom of the form are 'Go back' and 'Next' buttons.

パーソナルデータの各情報を英語で入力します。

開通までの流れ（アクティベート方法）




4) アクティベート完了



The screenshot shows the ChatSim website's activation confirmation page. At the top, there is a navigation bar with the ChatSim logo, links for Overview, Plan, Blog, Support, and Login, and buttons for Activate, Recharge, and Buy now. The main heading is "Activate your ChatSim". Below this, there are three icons: a smartphone, a person, and a checkmark, indicating the steps of the activation process. A green progress bar is shown below the icons. The text confirms that activation was completed successfully and provides a link to setup a smartphone. It also mentions a gift of 1000 credits for sharing the promotion code with friends. The promotion code "CAMEDIUW" is displayed in a green box. At the bottom, there are social media sharing icons and a list of participation rules.





ChatSim™ Overview Plan Blog Support Login Activate Recharge Buy now EN ▼

Activate your ChatSim

We confirm that activation was completed successfully.
You can start using your ChatSim soon.
[CLICK HERE](#) to setup your smartphone.

To thank you, ChatSim has a gift for you.
Invite all your friends to discover the service! Each time one of them uses the promotion code when activating,
we will give both of you a bonus recharge of 1000 credits.

Share your code:
CAMEDIUW

How to participate:

- Give the promotion code to be entered during activation to your friends who have purchased ChatSim;
- Both of you will immediately receive a free bonus recharge of 1000 credits;
- Your promotion code cannot be used for additional personal activations;
- Don't stop! Share your promotion code every time you want! Never-ending bonus recharges for you and your friends!

この画面が出たらアクティベート完了です！
後ほど、登録したメールアドレスにユーザー名とパスワードが届きます。次回からはこのユーザー名とパスワードでログインすることで個人ページにアクセスできます。

マルチメディアクレジット設定の仕方

ご利用の流れ（マルチメディアクレジット）

クレジット購入

クレジットをSIMに充当
英語サイト



マルチメディア
クレジット
開通

マルチメディアクレジットのご利用の場合は、
事前にマルチメディアクレジット購入をしてください。

マルチメディアクレジット購入

<http://chatsimjp.com/charge/>

マルチメディアクレジットをお使いのChat Simに充当
すると、写真や動画や音声通話がお楽しみいただけます。

クレジット消費は6つのゾーンで異なります。


詳しくは公式サイト内でご確認ください

<http://chatsimjp.com/multimedial-rates.html>

マルチメディアクレジット設定の仕方

マルチメディアクレジットの設定ページ

<https://www.chatsim.com/en/recharge>



The screenshot shows the 'Recharge your ChatSim' page. At the top, there is a navigation bar with links for Overview, Plan, Blog, Support, and Login, along with buttons for Activate, Recharge, and Buy now. The main heading is 'Recharge your ChatSim'. Below this, there are two input fields: 'E-mail' (with a red asterisk and the text '登録済みメールアドレス') containing 'XXX@XXX.XXX', and 'ChatSim Number' (with a red asterisk and the text '+44 で始まる番号') containing '+44XXXXXXXXXXXX'. Below these fields is a section for 'Recharge Import or type' with a red asterisk and the text 'こちらをクリック'. There are five options: 'Multimedia Recharge 2000 Credits (€10.00)', 'Multimedia Recharge 5000 Credits (€25.00)', 'Multimedia Recharge 10000 Credits (€50.00)', 'Multimedia Recharge with Pin' (which is highlighted with a red dashed box), and 'Recharge Plus 250 MB (€25.00)'. Below this section is a 'Pin' field (with a red asterisk and the text '購入済み PIN コード入力') containing 'XXXXXXXXXXXXXXXXXX'. At the bottom left, there is a checkbox for 'ChatSim の規約に同意' (I have read and accept the terms and conditions of ChatSim.) and a 'Send' button. A small note at the bottom left indicates 'Mandatory fields'.

必要事項と、事前購入したPINコードを入力することで、マルチメディアクレジットがチャージされます。複数のPINコードがある場合は、この作業を繰り返しおこなって下さい。


Android端末設定の仕方

- (1) Chatsimをセット
- (2) 設定> SIMカードにてChatsim番号のスポットを確認し、スポットをオンに設定



Android端末設定の仕方

(3) 設定>データ使用量にてモバイルデータをオンに設定。右上のメニューアイコンから「バックグラウンドデータを制限する」をクリック



Android端末設定の仕方

(4) 設定> モバイルネットワーク> アクセスポイント名にて新規作成を選び以下の内容で保存します

名前 : chatsim APN : chatsim

(5) スマートフォンを再起動します
※繋がらない時は、ユーザー名に+を入れず447から始まるChatsim Numberを入れ、パスワードに4桁のPINコードを入れて下さい。

